PS_VIEW v. 2.01 COMMANDS LIST (1)

(press PgDn or Esc)

Parameters	Command	Aliases	Description
(FILE_NAME)	o	a	open new picture
(FILE_NAME)	op	ap	open new paged document
	c	F10	redraw current picture
	i	F11	initialize parameter settings
	w	F12	view whole picture
{PAGE}	pn	np F4	go to the specified page
	pf	fp Home	go to the first page
	pl	lp End	go to the last page
{INCR}	n	PgDn	go to the next page
{INCR}	p	PgUp	go to the previous page
	g		draw local window-oriented coordinates grid
	gg		draw global coordinates grid (cm)
	ggg		draw global coordinates grid (cm, mm)
{HOR} {VER}	igg		initialize global grid origin
	wgg		initialize global grid origin to the window ori.
	dgg		initialize global grid origin to (0,0)
	gc		switch to global coordinates
	lc		switch to local coordinates

PS_VIEW v. 2.01 COMMANDS LIST (2)

(press PgUp, PgDn or Esc)

Parameters	Command	Aliases	Description
{MAG}	m		set magnification factor
{HOR} {VER}	v		view magnified and shifted picture
{HOR} {VER}	vu	Alt >	magnify picture (equiv. 'v')
{HOR} {VER}	vd	Alt <	diminish picture (equiv. 'v' with scaling $= \frac{1}{\mathrm{MAG}}$)
{HOR} {VER}	go	Tab	shift screen (equiv. 'v' with scaling $= 1$)
{SHIFT}	s		set shift
{SHIFT}	l	←	shift picture left
{SHIFT}	r	→	shift picture right
{SHIFT}	u	↑	shift picture up
{SHIFT}	d	↓	shift picture down
{STEP}	ro	Shift Tab	rotate by STEP $\times$ 90
	hf		flip picture horizontaly
	vf		flip picture verticaly
{INCR}	un	Del	undo previous picture
{INCR}	re	Ins	redo undone picture
	bb		show document bounding box
	pg		show document page box
	fr		show frame (printing area)

PS_VIEW v. 2.01 COMMANDS LIST (3) (press PgUp, PgDn or Esc)

Parameters	Command	Aliases	Description
{(FILE_NAME)}	pr	Ctrl Print Scr	print screen or send it to a file
DEVICE_NAME	prs		select printer (used by 'pr')
{(DEVICE)}	dev		select screen device
	r1024		set resolution (SVGA)
	r800		set resolution (SVGA)
	r640		set resolution (SVGA)
	rsc	F9	reset screen cursor
	e		try to recover from error (obsolete)
	q	Alt Q Alt F4	quit saving the restart
	x	Alt X Esc	exit without saving the restart
{(FILE_NAME)}	wr	F2	write the restart information
{(FILE_NAME)}	rr	F3	read the restart information
	help	Alt H F1	help
	ver		print PS_VIEW version
	rev		print Ghostscript revision

PS_VIEW v. 2.01 COMMANDS LIST (4) (press PgUp or Esc)

Remark 1: Optional parameters appear in curly braces.
Remark 2: Sequences in frames (keys) do not require pressing Enter,
they require, however, that ANSI.SYS is being installed.
Remark 3: Some commands change their meaning while the help is on.